Top Producer for Windows Mobile Quick Setup

Top Producer Systems Phone Number: 1-800-830-8300

Email: support@topproducer.com

Website: www.topproducer.com

Trademarks

Information in this document is subject to change without notice. Companies, names and data used in examples herein are fictitious unless otherwise noted, and are used for illustration purposes only. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, recording or otherwise for any purpose, without the express written permission of Top Producer Systems, a Move™ company, 4708 Caldwell Road East, Edgewood, WA 98372-9221 USA.

Top Producer[®], Top Producer[®] 7i, Top Producer for BlackBerry[®], Top Producer for Windows Mobile[®], Top Producer[®] 7i Remote, Top Producer[®] Assistant, Top Producer[®] 7i SellPhone[™], Top Producer[®] 7i for the Palm[™] handhelds, Top Connector[™] 7i, Broker Tools, Franchise Tools, Top Marketer[™] and Top Producer[®] Websites are trademarks of Top Producer Systems, a Move[™] company, 4708 Caldwell Road East, Edgewood, WA 98372-9221 USA.

Microsoft, Windows, Windows 95, Windows 98, Windows ME, Windows NT, Windows 2000, and Windows XP are trademarks of Microsoft Corporation.

Palm, Hotsync, Palm OS, and Palm Computing are trademarks of Palm Computing Inc., a 3Com Company.

Adobe Acrobat and Adobe Acrobat Reader are trademarks of Adobe Systems Incorporated.

The Sentry Spelling-Checker Engine © 2000 Wintertree Software Inc.

All other product names, company names, trademarks or service marks are the property of their respective owners.

© 2003-2008 TOP PRODUCER Systems Company. All rights reserved.

Document ID: 20060004.R3

Table Of Contents

Getting Started	1
What is Top Producer for Windows Mobile?	2
About this Guide	3
Contacting Technical Support	4
Before You Start Installing	5
System Requirements	6
Checklist for Getting Started	
Installing from Top Producer 7i	8
Step 1 - Assign a License	9
Step 2 - Set up Filters for Data Sent to the Handheld	11
Step 3 - Install the Software	12
Step 4 - Download Data onto your Handheld	14
Step 5 - Start up Top Producer for Windows Mobile	18
Installing from Top Producer 8i	20
Step 1 - Assign a License	21
Step 2 - Define a Filter and Install the Software	22
Step 3 - Download Data onto your Handheld	
Step 4 - Start up Top Producer for Windows Mobile	

Getting Started

In this chapter:

- "What is Top Producer for Windows Mobile?" on page 2
- "About this Guide" on page 3
- "Contacting Technical Support" on page 4

What is Top Producer for Windows Mobile?

Top Producer for Windows Mobile gives you access to your online Top Producer data any time, anywhere, with the portability of your handheld.

You can store listings, closings, contacts and leads on your handheld. You can also organize follow-up calls, appointments and to-dos with **Today's Activities**.

Synchronization technology ensures that the changes you make on your handheld (e.g. new contacts and new listings) are transferred into your online database after you perform a synchronization, and that changes made to the online database are transferred to the handheld.

About this Guide

This guide is in Portable Document Format (PDF), and is viewed using Adobe[®] Acrobat[®] Reader[®].

For more information about Adobe Acrobat, please refer to Adobe Acrobat's online Help. (To access the online Help from the main Adobe Acrobat window, click the **Help** menu, then **Reader Help**.)

How to Print the Guide

To print the guide:

- 1 From the **File** menu, click **Print**.
- 2 From the **Print** dialog box, set your printer options.
- 3 Click **OK**.

Navigating Within the Guide

If you are reading the guide online as a PDF file, click any text that appears in blue to jump directly to that section, (for example, click on "Installing from Top Producer 7i" on page 8).

Contacting Technical Support

Top Producer Technical Support is available Monday to Friday, 6:00 AM to 5:00 PM (Pacific Time):

• Email: support@topproducer.com

• Telephone: 1-800-830-8300

• **Fax**: 604-270-6365

Before You Start Installing

- "System Requirements" on page 6
- "Checklist for Getting Started" on page 7

System Requirements

To use Top Producer for Windows Mobile, your computer and handheld need to conform to the following requirements:

Memory

· Minimum 128 MB recommended

Computer operating system

· Windows 2000, XP or Vista

Internet browser

- Internet Explorer 6.0
- Top Producer 8i-related functions require Internet Explorer 7.0 or Firefox 2.0

Synchronization Software

- For Windows operating systems prior to Vista: ActiveSync 4.0 or higher
- For Windows Vista: Windows Mobile Device Center

Handheld operating system

Windows Mobile 5.0 (Pocket PC and Pocket PC Phone Editions)

Checklist for Getting Started

To set up Top Producer for Windows Mobile, ensure the following:

- That you have a Top Producer for Windows Mobile license.
- ActiveSync is installed on your computer.
- You can synchronize your handheld with ActiveSync.
- The handheld is connected to the USB port on your computer.

Note: For instructions on how to connect your handheld to your computer, refer to the instructions that came with your handheld.

Installing from Top Producer 7i

- "Step 1 Assign a License" on page 9
- "Step 2 Set up Filters for Data Sent to the Handheld" on page 11
- "Step 3 Install the Software" on page 12
- "Step 4 Download Data onto your Handheld" on page 14
- "Step 5 Start up Top Producer for Windows Mobile" on page 18

Step 1 - Assign a License

Follow these steps to make sure that you have been assigned a Top Producer for Windows Mobile license in Top Producer 7i.

To assign a license to an agent:

1 From Top Producer 7i's **Setup** menu, click **Agent setup**.

The Agent information page opens.

2 In the Additional Top Producer applications section, select Top Producer for Windows Mobile.

The displayed agent now has a Top Producer for Windows Mobile license.

3 Click OK.

To assign a license to an assistant:

Follow these steps if you purchased more than one license and want to assign a license to an assistant who also has a handheld device.

- 1 From the **Setup** menu in Top Producer 7i, click **Agent setup**.
- 2 From the *Agent information* page, click the **Assistants** action item on the left side of the screen.

The *Assistants* page opens.

Note: If you don't see your assistant's name in the list, you will need to add their information. For more information on creating assistants, see Top Producer 7i Quick Setup.

To purchase an assistant license, contact our Sales Department at 1-800-241-5309.

3 Select the assistant and then click the **View or edit** action item.

The Assistant information page opens.

4 In the **Login information** section, select **Top Producer for Windows Mobile** from the drop-down list and click **OK**.

The displayed assistant now has a Top Producer for Windows Mobile license.

Step 2 - Set up Filters for Data Sent to the Handheld

Set up filters to control which records are sent to your handheld. Doing this will speed-up your handheld's response time and limit the size of your database, making all of your synchronizations faster.

Setting up a Filter

To set up a filter:

- 1 From the Top Producer 7i **Setup** menu, select **Applications setup > Top Producer 7i for handhelds**.
- 2 Click the Filter action menu item.
- 3 From the *Filter for current device* screen, define the filter settings you want to use for your device.
 - For a complete listing of the fields available and how to use them, see the "Setting Up Filters to Control What Data is Sent to the Handheld" topic in the 7i online help.
- 4 By default, contacts and leads are only selected if they meet *all* of the filter conditions. If you have specified more than one filter condition and you want contacts to be selected that meet *any* of the conditions:
 - a) Click the **All** link to the right of the **Contacts and Leads** grid.

Note: This option is only available if you have more than one contact/lead filter set up.

b) From the *Filter group rule* dialog box, select **contact matches at least one condition** and click **OK**.

The **All** link changes to **Any**. Now contacts will be sent to the handheld if they match any one of the specified filter conditions.

5 When finished specifying your filter settings, click **OK**.

Step 3 - Install the Software

The following instructions assume you have the minimum system requirements installed. For more information, see "System Requirements" on page 6.

To install Top Producer for Windows Mobile:


- 1 Use the USB slot to connect your device to the computer.
- 2 From the Setup menu in Top Producer 7i, select Applications setup > TOP PRODUCER 7i for handhelds.
 - If you have any other mobile licenses, the *Register Device* dialog box opens.
- 3 Select the **Windows Mobile Handheld** radio button and then click **OK**.
- 4 From the *Handheld manager*, select the link to download the Windows Mobile handheld client software.
 - The File Download dialog box appears.
- 5 Click **Run**.
- 6 When the *Security Warning* dialog box appears, click **Run**.
- 7 Follow the on-screen prompts to install the software.
- 8 When the desktop installation is finished, a message will appear stating that the application will be installed on the next device connection. Click **OK**.

Note: If you are using an expansion memory card, you will be asked whether you wish to install to the handheld's base memory or to the expansion card. Only choose the latter if you are using a high-speed expansion card.

Important: You must install all of the files in just one of the two memory locations. If you don't do this - e.g. you install one file in the

handheld's base memory and the other two in the expansion card - Top Producer for Windows Mobile will not run.

9 When the handheld installation finishes, the following message appears:



10 Click **OK** to continue.

Top Producer for Windows Mobile is now installed on your handheld.


Step 4 - Download Data onto your Handheld

Downloading your Data


The first time you log onto Top Producer for Windows Mobile you will want to download your Top Producer 7i data onto your handheld.

To downloadTop Producer 7i data onto your handheld:

- 1 Connect your handheld to your computer via the USB port.
- 2 From the main screen's **Start** menu, select **Programs**. The **Launch Pad** will appear.




- 3 Tap the Top Producer icon. If this is the first time you've used Top Producer for Windows Mobile, you'll see a message asking you to log into Top Producer 7i to download your data.
- 4 Click **Yes** and the *Login* screen will appear.



5 Enter your Top Producer 7i username and password, then click **Connect** at the bottom left.

The message "connecting, please wait" will appear followed by "login successful." The FDR sequence will now proceed, displaying the sequence of messages shown below.



When this completes, click **OK**. The Top Producer for Windows Mobile screen will open and display your downloaded data.

Note: Depending on the size of your database and the way your filters are configured, FDR can take between 5 minutes to one hour to complete.

A Note for Windows Vista Users

If you are using Windows Vista and the FDR fails, displaying the message **Error 103**, please perform the following:

To redo FDR after receiving Error 103

- 1 From the Vista main screen, go to **Start** > **Control Panel** > **Windows Mobile Device Center**.
- 2 Click Mobile Device Settings and then Connections Settings. The Connections Settings screen opens.
- 3 From the **This computer is connected to** drop-down menu, select either **Work Network** or **The Internet**, then press **OK**.
- 4 Confirm that your Windows Mobile device is connected by viewing the bottom left corner of the Windows Mobile Device Center screen and confirming that the Connection status displays Connected.
- 5 If your mobile device is connected, restart the FDR process from Step 2 above. If not, contact Top Producer Technical support.

Step 5 - Start up Top Producer for Windows Mobile

The previous sections describe the steps needed for the first time you use Top Producer for Windows Mobile. The following steps describes how to start up the program after this.

Logging on from the Start Menu


To log onto Top Producer for Windows Mobile from the Start menu:

1 From the main screen's **Start** menu, select **Top Producer**.

The message Initializing Top Producer will appear. After this, the home screen will appear, displaying tabs for each object (e.g. Contacts, Leads, and Closings).

Note: We recommend that you keep Top Producer for Windows Mobile running constantly, and then shut it down at the end of the day.

While it is running, you can access other applications (such as PowerPoint) from the Start menu. To return to Top Producer from another application, click the Start menu's Top Producer icon.



Installing from Top Producer 8i

- "Step 1 Assign a License" on page 21
- "Step 2 Define a Filter and Install the Software" on page 22
- "Step 3 Download Data onto your Handheld" on page 25
- "Step 4 Start up Top Producer for Windows Mobile" on page 29

Step 1 - Assign a License

Follow these steps to make sure that you have been assigned a Top Producer for Windows Mobile license in Top Producer 8i.

To view your active licenses:

- 1 From the **Utility menu** of Top Producer 8i, click **My Account**.
- 2 The header of the My Account screen displays every active license you have for your Top Producer account. Top Producer for Windows Mobile should be present.
- 3 If no license is present, contact Top Producer. If you are a part of a Broker account, contact your Responsible Agent.

To assign a license to an assistant:

Follow these steps if you purchased more than one license and want to assign a license to an assistant who also has a handheld device.

- 1 From the **Utility menu** of Top Producer 8i, select **My Account**.
- 2 Select the Team Members tab.
- 3 Click on the assistant's name in the Assistants table.
- 4 Click the **Edit Assistant Info** link in the bottom left.
- 5 From the Assign Licenses and Feature Access fieldset, select the Give the assistant access to check box and select Top Producer 8i for Windows Mobile from the drop-down list.
- 6 Click the Save Assistant Info button.

Step 2 - Define a Filter and Install the Software

The following instructions assume you have the minimum system requirements installed. For more information, see *"System Requirements"* on page 6.

To install Top Producer for Windows Mobile:

- 1 Use the USB slot to connect your device to your computer.
- 2 From the Main Menu of Top Producer 8i select the **Mobility** icon.
- 3 From the My Device tab, click the Register a Device link.
- 4 From the *Register a Device Step 1* screen, select the **Windows Mobile** radio button and click **Next**.
- 5 From the *Register a Device Step 2* screen, define the filter settings that you want to use for your device.
 - For a complete listing of the fields available and how to use them, see the "Filter subtab" topic in the 8i online help.
- 6 When defining your filter settings for **Contacts & Leads**, pay particular attention to the **To Match** radio buttons.
 - Selecting the All conditions must be met radio button will result in the criteria you defined being connected with AND statements (i.e. if you specified a Zip code and an area code, only contacts matching both criteria will be synchronized).
 - Selecting the Match any conditions radio button will result in the criteria you defined being connected with OR statements (i.e. if you specified a Zip code and an area code, contacts matching either criteria will be synchronized).

Note: The only exception to the To Match setting concerns the multi-select picklists used for the Contact Type, State, and Country fields. The selections you make in the multi-pick picklists are joined internally by OR statements, regardless of the To Match setting. For example, filtering settings including Contact Types and States criteria would be applied as follows: Contact_Types[Buyer OR Seller] AND State[Washington OR Oregon OR Ohio]. This would match Buyers and Sellers from any of the three states specified.


- 7 Click the **Next** button.
- 8 From the *Register a Device Step 3* screen, click the **Windows Mobile Client Software** link.

The File Download dialog box appears.

- 9 Click Run.
- 10 When the *Security Warning* dialog box appears, click **Run**.
- 11 Follow the on-screen prompts to install the software.
- 12 When the desktop installation is finished, a message will appear stating that the application will be installed on the next device connection. Click **OK**.

Note: If you are using an expansion memory card, you will be asked whether you wish to install to the handheld's base memory or to the expansion card. Only choose the latter if you are using a high-speed expansion card. Always install all of the files in just one of the two memory locations. If you don't do this - e.g. you install one file in the handheld's base memory and the other two in the expansion card - Top Producer for Windows Mobile will not run.

13 When the handheld installation finishes, the following message appears:



14 Click **OK** to continue. Top Producer for Windows Mobile is now installed on your handheld.


Step 3 - Download Data onto your Handheld

Downloading your Data

The first time you log onto Top Producer for Windows Mobile you will want to download your Top Producer 8i data onto your handheld.

To download Top Producer 8i data onto your handheld:

- 1 Connect your handheld to your computer via the USB port.
- 2 From the main screen's **Start** menu, select **Programs**. The **Launch Pad** will appear.



3 Tap the Top Producer icon. If this is the first time you've used Top Producer for Windows Mobile, you'll see a


message asking you to log into Top Producer 8i to download your data.

4 Click **Yes** and the *Login* screen will appear.



5 Enter your Top Producer 7i username and password, then click **Connect** at the bottom left.

The message "connecting, please wait" will appear followed by "login successful." The FDR sequence will now proceed, displaying the sequence of messages shown below..



6 When this completes, click **OK**. The Top Producer for Windows Mobile screen will open and display your downloaded data.

Note: Depending on the size of your database and the way your filters are configured, FDR can take between 5 minutes to one hour to complete.

A Note for Windows Vista Users

If you are using Windows Vista and the FDR fails, displaying the message **Error 103**, please perform the following:

To redo FDR after receiving Error 103

- 1 From the Vista main screen, go to **Start** > **Control Panel** > **Windows Mobile Device Center**.
- 2 Click Mobile Device Settings and then Connections Settings. The Connections Settings screen opens.
- 3 From the **This computer is connected to** drop-down menu, select either **Work Network** or **The Internet**, then press **OK**.
- 4 Confirm that your Windows Mobile device is connected by viewing the bottom left corner of the Windows Mobile Device Center screen and confirming that the Connection status displays Connected.
- 5 If your mobile device is connected, restart the FDR process from Step 2 above. If not, contact Top Producer Technical support.

Step 4 - Start up Top Producer for Windows Mobile

The previous sections describe the steps needed for the first time you use Top Producer for Windows Mobile. The following steps describes how to start up the program after this.

Logging on from the Start Menu

To log onto Top Producer for Windows Mobile from the Start menu:

We recommend that you keep Top Producer for Windows Mobile running constantly, and then shut it down at the end of the day.

While it is running, you can access other applications (such as PowerPoint) from the Start menu. To return to Top Producer from another application, click the Start menu's Top Producer icon.

1 From the main screen's Start menu, select Top Producer.

The message **Initializing Top Producer** will appear. After this, the home screen will appear, displaying tabs for each object (e.g. **Contacts**, **Leads**, and **Closings**).